



Screen Shooting Show R.1024




Quick User's Manual

1. After you start SSS the windows may have wrong dimensions...
First change basic settings. Button “Screen Settings” on top left corner in lower menu window.




Chose smallest “Screen Resolution” for easier configuration.




2. The windows layout will look like here...

Next chose correct Port where KES data comes from a list “Connect to port”:


- COM1, COM2... for physical COM-port and virtual USB COM-port of your PC;
- “Add port”, and type IP address with port number for MOXA, like 192.168.127.254:4002 (please, ensure that COM-port settings on PC or in MOXA configuration is set as 19200 bod).




3. Set “Connect to port when program starts” in check-box.




4. Next “Screen Settings” can be configured for your needs: number of bullets (5 or 8), high contrast bullets, color scheme, use compact font for shooter names, small and full screen resolution. When you may close Settings Window.




5. Press button “Show Start List”




6. Press button "Import Start List"




6. Open text file with Start List in KES format.




You will have a list for all athletes in appropriate window.



- Now you will have real-time shooting graphics on top left "Targets" window. You may set "Show Now Shooting Only" in check-box and see only Athletes at shooting range in a list.



8. For FULL-SCREEN MODE press **Ctrl+M**



To go back to Small-screen mode press **Ctrl+M** again.

9. In order to show full-screen mode on LED Videowall, make following:

- Connect video-processor or capture card of Videowall to you laptop via HDMI or DVI input.
- Set this screen as second clone monitor in your laptop.
- Set resolution 1024x768 for this monitor in your laptop.
- Set “stretch” or “fit to screen” mode in video-processor or capture card of Videowall.

9. In order to play KES-log on software for demonstration, make following:

- Go back to Small-screen mode, put mouse on main control winow.
- Press **Alt+L** ;
- Press button “From file” and open KES-log. It starts to play automatically.
- You may put a pause and continue playing here in a window.

